

The `minitoc` package

Jean-Pierre F. Drucbert
ONERA / Centre de Toulouse / SRI
`drucbert@onecert.fr`

2000/12/08

Contents

1	The minitoc package	7
1.1	Introduction	8
1.2	Usage	9
1.2.1	Fonts and Titles	13
1.2.2	Special Features	18
1.2.3	Usage with MS-DOS	21
1.3	The <code>mtcoff</code> package	23
2	Frequently Asked Questions	25

List of Tables

1.1	Commands for a <code>minitoc</code>	10
1.2	Commands for a <code>secttoc</code>	11
1.3	Commands for a <code>parttoc</code>	12
1.4	Commands to add an entry in the table of contents for a starred chapter, section or part.	14
1.5	Fonts for the <code>\part...</code> , <code>\mini...</code> and <code>\sect...</code> commands. .	15
1.6	Fonts for the table entries.	16
1.7	Available languages	22

Chapter 1

The minitoc package

Contents

1.1	Introduction	8
1.2	Usage	9
1.2.1	Fonts and Titles	13
1.2.2	Special Features	18
1.2.2.1	Horizontal Rules	18
1.2.2.2	Page Numbers, Leaders	18
1.2.2.3	Features for <code>parttoc-s</code>	19
1.2.2.4	The “Chapter 0” Problem	20
1.2.2.5	Special Entries	20
1.2.3	Usage with MS-DOS	21
1.3	The <code>mtcoff</code> package	23

Tables

1.1	Commands for a <code>minitoc</code>	10
1.2	Commands for a <code>secttoc</code>	11
1.3	Commands for a <code>parttoc</code>	12
1.4	Commands to add an entry in the table of contents for a starred chapter, section or part.	14
1.5	Fonts for the <code>\part...</code> , <code>\mini...</code> and <code>\sect...</code> commands.	15
1.6	Fonts for the table entries.	16
1.7	Available languages	22

1.1 Introduction

This package, initially written by Nigel Ward and Dan Jurafsky, has been almost completely redesigned at ONERA/Centre de Toulouse by Jean-Pierre Drucbert. It creates a mini-table of contents (a “minitoc”¹) at the beginning of each chapter of the document. It is also possible to have a mini-list of figures (a “minilof”) and a mini-list of tables (a “minilot”). The document class should of course define chapters (styles like `book` or `report`) or sections (styles like `article`). Thus, this package should not be used with document classes without sectioning commands (like `letter`). When the document class defines a “part” sectioning level (i.e. classes like `book`, `report` and `article`), you can create a “partial” table of contents (a “parttoc”) at the beginning of each part of the document. It is also possible to have a partial list of figures (a “partlof”) and a partial list of tables (a “partlot”). When the document class has no `\chapter` command but has a `\section` command, you may use section level tables of contents (“secttoc”) at the beginning of each section. **Note:** you cannot use chapter level and section level table of contents in the same document. This restriction is intended to avoid documents full of local tables of contents, list of figures and tables at every sectioning level.



The current version of this package is #34.



Note: the commands relative to the part level are defined only if the document class defines `\part`. The commands relative to the section level are defined only if the document class does not define `\chapter`.

Licence

It may be distributed and/or modified under the conditions of the LaTeX Project Public License, either version 1.1 of this license or (at your option) any later version. The latest version of this license is in

<http://www.latex-project.org/lppl.txt>

¹The `minitoc` package introduces its own jargon, explained in this note. It should not be too difficult, however, to learn and use.

and version 1.1 or later is part of all distributions of LaTeX version 1999/06/01 or later.

But please don't bother me about hacked versions.

1.2 Usage

To use the `minitoc` package, you must introduce a command

```
\usepackage{minitoc}
```

in the preamble of your document. The mini-table of contents will appear in the chapter, after the `\chapter` command, at the point of the `\minitoc` command. The `\minitoc` command may occur *anywhere* inside a chapter. Of course, it is better to put it at the beginning of the chapter, eventually after some introductory material. But you can also decide to put it at the end of the chapter. You should use the same conventions in all chapters. If you want to add the mini-table of contents for a chapter, you must use the sequence given in Table 1.1 For each mini-table of contents, an auxiliary file will be created with a name of the form $\langle document \rangle.mtc\langle N \rangle$, where $\langle N \rangle$ is the absolute chapter number. “Absolute” means that this number is unique, and increasing from the first chapter. The suffix is `.mlf` $\langle N \rangle$ for mini-lists of figures and is `.mlt` $\langle N \rangle$ for mini-lists of tables. (If you are under MS-DOS or any operating system with short extensions to filenames, see Section 1.2.3 and Chapter 2, item 5).

The section-level table of contents will appear in the section, after the `\section` command, at the point of the `secttoc` command. The `\secttoc` command may occur *anywhere* inside a section. Of course, it is better to put it at the beginning of the section, eventually after some introductory material. You should use the same conventions in all sections. If you want to add the section-level table of contents for a section, you must use the sequence given in Table 1.2 For each section-level table of contents, an auxiliary file will be created with a name of the form $\langle document \rangle.stc\langle N \rangle$, where $\langle N \rangle$ is the absolute section number. The suffix is `.slf` $\langle N \rangle$ for section-level lists of figures and is `.slt` $\langle N \rangle$ for section-level lists of tables. (If you are under MS-DOS or any operating system with short extensions to filenames, see Section 1.2.3 and Chapter 2, item 5).

Table 1.1: Commands for a minitoc

```

\documentclass[...] {book}
\usepackage{minitoc}
...
\setcounter{minitocdepth}{2}           default
\setlength{\mtcindent}{24pt}          default
\renewcommand{\mtcfont}{\small\rm}    default
\renewcommand{\mtcSfont}{\small\bf}   default
...
\begin{document}
...
\dominitoc
\dominilof
\dominilot
\tableofcontents                       or \faketableofcontents
\listoffigures                         or \fakelistoffigures
\listoftables                          or \fakelistoftables
...
\chapter{...}
\minitoc                               if you want one
\minilof                               if you want one
\minilot                               if you want one
...

```

If you want to add the partial table of contents for a part, you must use the sequence given in Table 1.3. For each partial table of contents, an auxiliary file will be created with a name of the form $\langle document \rangle.ptc\langle N \rangle$, where $\langle N \rangle$ is the part number. The suffix is $.plf\langle N \rangle$ for partial lists of figures and is $.plt\langle N \rangle$ for partial lists of tables. (If you are under MS-DOS or any operating system with short extensions to filenames, see Section 1.2.3 and Chapter 2, item 5).



Note: the user is responsible of requiring or not requiring a mini-toc (lof or lot) for some chapter. Asking a minilof for a chapter without any figure will result in an empty and ugly mini list of figures (i.e. the title and two horizontal rules). He is also responsible of requiring or not requiring a partial toc (lof or lot) for some part. Asking a partlof for a part without any figure

Table 1.2: Commands for a secttoc

<code>\documentclass[...]{article}</code>	
<code>\usepackage{minitoc}</code>	
<code>...</code>	
<code>\setcounter{\secttocdepth}{2}</code>	<i>default</i>
<code>\setlength{\stcindent}{24pt}</code>	<i>default</i>
<code>\renewcommand{\stcfont}{\small\rm}</code>	<i>default</i>
<code>\renewcommand{\stcSSfont}{\small\bf}</code>	<i>default</i>
<code>...</code>	
<code>\begin{document}</code>	
<code>...</code>	
<code>\dosecttoc</code>	
<code>\dosectlof</code>	
<code>\dosectlot</code>	
<code>\tableofcontents</code>	<i>or \faketableofcontents</i>
<code>\listoffigures</code>	<i>or \fakelistoffigures</i>
<code>\listoftables</code>	<i>or \fakelistoftables</i>
<code>...</code>	
<code>\chapter{...}</code>	
<code>\secttoc</code>	<i>if you want one</i>
<code>\sectlof</code>	<i>if you want one</i>
<code>\sectlot</code>	<i>if you want one</i>
<code>...</code>	

will result in an empty and ugly part list of figures (i.e. the title alone on a page). Analogous remarks apply to section-level tables of contents (secttoc, sectlof and sectlot).

By default, the mini-tables and partial tables of contents contain only references to sections and subsections. The `minitocdepth` and `parttocdepth` counters, similar to `tocdepth`, allows the user to modify this behaviour. Mini or partial lists of figures or tables are not affected by the value of these counters.

NOTE: if you are using `\chapter*` and a



`\addcontentsline{toc}{chapter}{...}`

Table 1.3: Commands for a parttoc

<code>\documentclass[...]{book}</code>	
<code>\usepackage{minitoc}</code>	
<code>...</code>	
<code>\setcounter{parttocdepth}{2}</code>	<i>default</i>
<code>\setlength{\ptcindent}{0pt}</code>	<i>default</i>
<code>\renewcommand{\ptcfont}{\normalsize\rm}</code>	<i>default</i>
<code>\renewcommand{\ptcCfont}{\normalsize\bf}</code>	<i>default</i>
<code>\renewcommand{\ptcSfont}{\normalsize\rm}</code>	<i>default</i>
<code>...</code>	
<code>\begin{document}</code>	
<code>...</code>	
<code>\doparttoc</code>	
<code>\dopartlof</code>	
<code>\dopartlot</code>	
<code>\tableofcontents</code>	<i>or</i>
	<code>\faketableofcontents</code>
<code>\listoffigures</code>	<i>or</i>
	<code>\fakelistoffigures</code>
<code>\listoftables</code>	<i>or</i>
	<code>\fakelistoftables</code>
<code>...</code>	
<code>\part{...}</code>	
<code>\parttoc</code>	<i>if you want one</i>
<code>\partlof</code>	<i>if you want one</i>
<code>\partlot</code>	<i>if you want one</i>
<code>...</code>	

command to add something in the table of contents, the numbering of minitoc files would be altered. To avoid that problem, say

```

\addstarredpart{...}
\addstarredchapter{...}
\addstarredsection{...}

```

These commands apply only for the level of a part-, mini- or sect-toc; for lower levels, use

```
\addcontentsline{toc}{section}{...}
```

by example, to add a section-level entry in the toc and the minitoc:

```
\chapter*{Title of chapter}
\addstarredchapter{Title of chapter}
\minitoc
\section*{First section}
\addcontentsline{toc}{section}{First section}
\section*{Second section}
\addcontentsline{toc}{section}{Second section}
```

There is sometimes a problem with minitocs (and siblings) when you use `\chapter*` (or `\section*`): the minitocs appear in the wrong chapter. You can add a `\adjustmtc` (or `\adjuststc` or `\adjustptc`) command at the end of the starred chapter (or section or part) to increment the corresponding counter. Do not use things like `\stepcounter{mtc}` (which should work), because the `mtcoff` package knows what to do about `\adjustmtc` (and others), but can do nothing about `\stepcounter`.

A more clever way to solve this problem is to use commands like:

```
\mtcaddchapter[⟨title⟩]
```

which adds an entry in the table of contents (and adjusts the counter, because it calls `\adjustmtc`). The table 1.4 summarizes these commands, that you put *after* `\chapter*`, etc. If the optional argument is omitted or empty or blank, no entry will be visible in the table of contents nor in the minitocs. If the optional argument is something invisible (like `~` or `\quad`), the result will be strange but logically correct.

1.2.1 Fonts and Titles

The mini and partial tables and lists are typeset in a **verse**-like environment, and can be split over pages. The mini-table of contents is typeset in the `\mtcfont` font, which is `\small\rm` by default. Section entries

Table 1.4: Commands to add an entry in the table of contents for a starred chapter, section or part.

Level	With title
chapter	<code>\mtcaddchapter[<i><title></i>]</code>
section	<code>\mtcaddsection[<i><title></i>]</code>
part	<code>\mtcaddpart[<i><title></i>]</code>

are typeset in the `\mtcSfont` font, which is `\small\bf` by default. For subsections, subsubsections, paragraphs and subparagraphs, the commands `\mtcSSfont`, `\mtcSSSfont`, `\mtcPfont` and `\mtcSPfont` are available (by default, `\small\rm`) to enable the use of various fonts. Mini lists of figures and tables are typeset in the fonts `\mlffont` and `\mltfont`, which are `\small\rm` by default. Tables 1.5 and 1.6 summarize these many commands².

Titles are typeset in the `\mtifont` (`\large\bf` by default) font and the texts of the titles are defined by `\mtctitle`, `\mlftitle` and `\mlttitle`, which are the strings “Contents”, “Figures” and “Tables” by default. These commands should be redefined by `\renewcommand` for languages other than english. The language option files like `french.mld` and `english.mld`³ (and others⁴) are available. You can easily prepare a similar file for your preferred language.

The partial table of contents is typeset in the `\ptcfont` font, which is defined as `\normalsize\rm` by default. Chapter entries are typeset in the `\ptcCfont` font, which is `\normalsize\bf` by default. Section entries are typeset in the `\ptcSfont` font, which is `\normalsize\rm` by default. For subsections, subsubsections, paragraphs and subparagraphs, the commands `\ptcSSfont`, `\ptcSSSfont`, `\ptcPfont` and `\ptcSPfont` are available (by default, `\normalsize\rm`) if you want to use various fonts. Partial lists of figures and tables are typeset in the fonts `\mlffont` and `\mltfont`, which are `\normalsize\rm` by default.

²These tables were contributed by Stefan Ulrich. Thanks to him.

³The suffix `.mld` means “minitoc language definition (file)”.

⁴Most of the strings defined in these language option files were taken from the superb **Babel** system by Johannes Braams and some were adapted, others were offered by gentle users or taken from specific packages, like `ArabTeX` or `vietnam.sty`. Other languages are welcome.

Table 1.5: Fonts for the `\part...`, `\mini...` and `\sect...` commands.

Command	Font default setting	Title string default setting	Title font default setting
For the <code>\part...</code> commands:			
<code>\parttoc</code>	<code>\ptcfont</code> <code>\normalsize\rm*</code> <code>\small\rm**</code>	<code>\ptctitle</code> Table of Contents [†]	<code>\ptifont</code> <code>\Huge\bf*</code> <code>\large\bf**</code>
<code>\partlof</code>	<code>\plffont</code> <code>\normalsize\rm*</code> <code>\small\rm**</code>	<code>\plftitle</code> List of Figures [†]	<code>\ptifont</code> <code>\Huge\bf*</code> <code>\large\bf**</code>
<code>\partlot</code>	<code>\pltfont</code> <code>\normalsize\rm*</code> <code>\small\rm**</code>	<code>\plttitle</code> List of Tables [†]	<code>\ptifont</code> <code>\Huge\bf*</code> <code>\large\bf**</code>
For the <code>\mini...</code> commands:*			
<code>\minitoc</code>	<code>\mtcfont</code> <code>\normalsize\rm</code>	<code>\mtctitle</code> Contents [†]	<code>\mtifont</code> <code>\large\bf</code>
<code>\minilof</code>	<code>\mlffont</code> <code>\small\rm</code>	<code>\mlftitle</code> Figures [†]	<code>\mtifont</code> <code>\large\bf</code>
<code>\minilot</code>	<code>\mltfont</code> <code>\small\rm</code>	<code>\plttitle</code> Tables [†]	<code>\mtifont</code> <code>\large\bf</code>
For the <code>\sect...</code> commands:**			
<code>\secttoc</code>	<code>\stcfont</code> <code>\normalsize\rm</code>	<code>\stctitle</code> Contents [†]	<code>\stifont</code> <code>\large\bf</code>
<code>\sectlof</code>	<code>\slffont</code> <code>\small\rm</code>	<code>\mlftitle</code> Figures [†]	<code>\stifont</code> <code>\large\bf</code>
<code>\sectlot</code>	<code>\sltfont</code> <code>\small\rm</code>	<code>\plttitle</code> Tables [†]	<code>\stifont</code> <code>\large\bf</code>

*for documentclasses with `\chapter` level (e.g. `book`, `report`)

**for documentclasses with no `\chapter` level (e.g. `article`)

[†]default for english; changed by the language definition files

Titles are typeset in the `\ptifont` (`\Huge\bf` by default) font and the texts of the titles are defined by `\ptctitle`, `\plftitle` and `\plttitle`, which are the strings “Table of Contents”, “List of Figures” and “List of Tables” by default. These commands should be redefined by `\renewcommand` for languages other than english. The language option files like `french.mld` and `english.mld` (and many others, see footnote 4 above) are available. You can easily prepare a similar style for your preferred language.

The section-level table of contents is typeset in the `\stcfont` font, which is defined as `\normalsize\rm` by default. Subsection entries are typeset

Table 1.6: Fonts for the table entries.

Level	Font	default setting
For the <code>\parttoc</code> entries:		
Chapter*	<code>\ptcCfont*</code>	<code>\normalsize\bf*</code>
Section	<code>\ptcSfont</code>	<code>\normalsize\rm*</code> <code>\small\bf**</code>
Subsection	<code>\ptcSSfont</code>	<i>(like <code>\ptcfont</code>)</i>
Subsubsection	<code>\ptcSSfont</code>	<i>(like <code>\ptcfont</code>)</i>
Paragraph	<code>\ptcPfont</code>	<i>(like <code>\ptcfont</code>)</i>
Subparagraph	<code>\ptcSPfont</code>	<i>(like <code>\ptcfont</code>)</i>
For the <code>\minitoc</code> entries:*		
Section	<code>\mtcSfont</code>	<code>\small\bf</code>
Subsection	<code>\mtcSSfont</code>	<i>(like <code>\mtcfont</code>)</i>
Subsubsection	<code>\mtcSSfont</code>	<i>(like <code>\mtcfont</code>)</i>
Paragraph	<code>\mtcPfont</code>	<i>(like <code>\mtcfont</code>)</i>
Subparagraph	<code>\mtcSPfont</code>	<i>(like <code>\mtcfont</code>)</i>
For the <code>\secttoc</code> entries:**		
Subsection	<code>\stcSSfont</code>	<code>\normalsize\bf</code>
Subsubsection	<code>\stcSSfont</code>	<i>(like <code>\stcfont</code>)</i>
Paragraph	<code>\stcPfont</code>	<i>(like <code>\stcfont</code>)</i>
Subparagraph	<code>\stcSPfont</code>	<i>(like <code>\stcfont</code>)</i>

*for documentclasses with `\chapter` level (e.g. `book`, `report`)

**for documentclasses with no `\chapter` level (e.g. `article`)

in the `\stcSSfont` font, which is `\normalsize\bf` by default. Subsubsection entries are typeset in the `\stcSSfont` font, which is `\normalsize\rm` by default. For subsubsections, paragraphs and subparagraphs, the commands `\stcSSfont`, `\stcPfont` and `\stcSPfont` are available (by default, `\normalsize\rm`) if you want to use various fonts. Partial lists of figures and tables are typeset in the fonts `\slffont` and `\sltfont`, which are defined as `\normalsize\rm` by default.

Titles are typeset in the `\stifont` (`\normalsize\bf` by default) font and the texts of the titles are defined by `\stctitle`, `\slftitle` and `\slttitle`, which are the strings “Contents”, “Figures” and “Tables” by default. These commands should be redefined by `\renewcommand` for languages other than english. The language option files like `french.mld` and `english.mld` (and some others, see footnote 4 above) are available. You can easily prepare a similar style for your preferred language.

By default, titles are on the left. The commands `\dominitoc`, `\dominilof` and `\dominilot` accept an optional argument to change the default position of the corresponding title: `[l]` for left (default), `[c]` for center, `[r]` for right, or `[e]` (or `[n]`) for empty (no title). The change is global for all the document.

If you want to change the position of the title for only one minitoc (or minilof or minilot), just use such an optional argument with the command `\minitoc` (or `\minilof` or `\minilot`).

By default, titles are on the left. The commands `\doparttoc`, `\dopartlof` and `\dopartlot` accept an optional argument to change the default position of the corresponding title: `[l]` for left (default), `[c]` for center, `[r]` for right, or `[e]` (or `[n]`) for empty (no title). The change is global for all the document.

By default, titles are on the left. The commands `\dosecttoc`, `\dosectlof` and `\dosectlot` accept an optional argument to change the default position of the corresponding title: `[l]` for left (default), `[c]` for center, `[r]` for right, or `[e]` (or `[n]`) for empty (no title). The change is global for all the document.

If you want to change the position of the title for only one secttoc (or sectlof or sectlot), just use such an optional argument with the command `\secttoc` (or `\sectlof` or `\sectlot`).

To summarize: by default, all titles are on the left. However, each one of the following commands:

```
\doparttoc, \dopartlof, \dopartlot,
\dominitoc, \dominilof, \dominilot,
\dosecttoc, \dosectlof, \dosectlot,
\parttoc, \partlof, \partlot,
\minitoc, \minilof, \minilot,
\secttoc, \sectlof, \sectlot
```

accepts an optional argument to change the positioning of the title: `[l]` for left (default), `[c]` for center, `[r]` for right, `[e]` or `[n]` for empty (no title). The arguments for the `\do...` commands change the positioning of all corresponding titles of the document. For the other commands, the options only change the formatting of the current heading.

With the commands `\tightmtctrue` (or the `tight` package option) and `\tightmtcfalse` (or the `loose` package option, which is the default), the minitocs (minilofs, etc.) will have less (tight) or more (loose) space between contents lines.

The mini-tables and lists, as partial and section-level tables and lists, are using some space on the first pages on each chapter, part or section, thus the page numbers are altered. After the first \LaTeX run, the mini-tables and lists, partial tables and lists and section-level tables and lists will be empty; after the second run, they appear, but because they modify the page numbering, page numbers are wrong; after the third \LaTeX run, the mini, partial and section-level tables and lists should be correct.

1.2.2 Special Features

1.2.2.1 Horizontal Rules

By default, most of minitocs and siblings have horizontal rules after their titles and at their ends. The exception is the “partoc” in a book- or report-like document (i.e. when `\chapter` is defined). To activate or deactivate these rules, the following commands are available:

				defaults for		
	rules in		no rules in	book	report	article
<code>\ptcrule</code>	parttocs	<code>\noptcrule</code>	parttocs	N	N	Y
<code>\mtcrule</code>	minitocs	<code>\nomtcrule</code>	minitocs	Y	Y	N-A
<code>\stcrule</code>	secttocs	<code>\nostcrule</code>	secttocs	N-A	N-A	Y

1.2.2.2 Page Numbers, Leaders

By default, the page numbers are listed in each minitoc, minilof, etc. Some authors want only the section titles (with the section numbers), but not the page numbers. Hence the obvious declarations below are available:

Type	Page numbers (Default)	No page numbers
minitoc	<code>\mtcpagenumbers</code>	<code>\nomtcpagenumbers</code>
secttoc	<code>\stcpagenumbers</code>	<code>\nostcpagenumbers</code>
parttoc	<code>\ptcpagenumbers</code>	<code>\noptcpagenumbers</code>
minilof	<code>\mlfpagenumbers</code>	<code>\nomlfpagenumbers</code>
sectlof	<code>\slfpagenumbers</code>	<code>\noslfpagenumbers</code>
partlof	<code>\plfpagenumbers</code>	<code>\noplfpagenumbers</code>
minilot	<code>\mltpagenumbers</code>	<code>\nomltpagenumbers</code>
sectlot	<code>\sltpagenumbers</code>	<code>\nosltpagenumbers</code>
partlot	<code>\pltpagenumbers</code>	<code>\nopltpagenumbers</code>

In the minitocs and siblings, they are leaders of dots between the section titles and the page numbers. The `undotted` package option removes these dots. The `dotted` option is the default.

1.2.2.3 Features for parttoc-s

By default, a `parttoc` (or a `partlof` or a `partlot`) is preceded and followed by a `\cleardoublepage`, and has a page style of `empty`. Since version #32, you can modify this behaviour by redefining the following commands, whose meaning is obvious:

Type	Command	Default
<code>parttoc</code>	<code>\beforeparttoc</code>	<code>\cleardoublepage</code>
<code>parttoc</code>	<code>\afterparttoc</code>	<code>\cleardoublepage</code>
<code>parttoc</code>	<code>\thispageparttocstyle</code>	<code>\thispagestyle{empty}</code>
<code>partlof</code>	<code>\beforepartlof</code>	<code>\cleardoublepage</code>
<code>partlof</code>	<code>\afterpartlof</code>	<code>\cleardoublepage</code>
<code>partlof</code>	<code>\thispagepartlofstyle</code>	<code>\thispagestyle{empty}</code>
<code>partlot</code>	<code>\beforepartlot</code>	<code>\cleardoublepage</code>
<code>partlot</code>	<code>\afterpartlot</code>	<code>\cleardoublepage</code>
<code>partlot</code>	<code>\thispagepartlotstyle</code>	<code>\thispagestyle{empty}</code>

1.2.2.4 The “Chapter 0” Problem

Some documents do not begin with chapter number one, but with chapter number zero (or even a weirder number). To make the `minitoc` package work with such documents, you must insert the command

```
\firstchapteris{⟨N⟩}
```

before the `\dominitoc` and analogous commands. $\langle N \rangle$ is the number of your first chapter. This command *does not* modify the numbering of chapters, you must use a `\addtocounter{chapter}{-1}` command to get a first chapter numbered 0. The `\firstpartis` and `\firstsectionis` commands are analogous for parts and sections with a non standard numbering.



Since version #17c, these commands are obsolete, as this problem has been solved. Thus they just give a harmless warning.

1.2.2.5 Special Entries⁵



If you want to add entries in the Table of Contents for objects like the Table of Contents itself, the List of Figures, the List of Tables, the Bibliography or the Index, you should use the `tocbibend` package from Peter R. Wilson (this package is available from the CTAN archives).

But these entries are considered as chapters (or sections in an article class document) when the `.toc` file is scanned to prepare the minitocs (the `\dominitoc` phase).

So you must add an `\mtcaddchapter` command, *without argument*, after the commands `\tableofcontents`, `\listoffigures` and `\listoftables`.

For the bibliography, you should add a `\adjustmtc` command after the `\bibliography` command.

For the index, it is a bit more complicated, you add the following commands just after the `\printindex` command:

⁵**Warning:** these features are still experimental.

```

\addcontentsline{lof}{xchapter}{}
\addcontentsline{lot}{xchapter}{}
\mtcaddchapter

```

Of course, in documents where the TOC, LOF, LOT, bibliography and/or index are processed as starred sections, you must modify these additions to use section level commands.

And proceed with care, tracking in the `.log` file the insertion of `.mtcN` files (and siblings). You have some examples in the `add.tex` file distributed with `minitoc`.

1.2.3 Usage with MS-DOS

Under MS-DOS (and other PC oriented operating systems), the filename extensions are limited to 3 characters. The `minitoc` package determines dynamically the type of extensions available and will use it. All other modifications will be done automatically. The `.mtc⟨N⟩` suffix will become `.M⟨N⟩`, where `⟨N⟩` is the absolute chapter number. The suffixes `.mlf⟨N⟩` and `.mlt⟨N⟩` become `.F⟨N⟩` and `.T⟨N⟩`. The `.ptc⟨N⟩` suffix will become `.P⟨N⟩`, where `⟨N⟩` is the part number. The suffixes `.plf⟨N⟩` and `.plt⟨N⟩` become `.G⟨N⟩` and `.U⟨N⟩`. The `.stc⟨N⟩` suffix will become `.S⟨N⟩`, where `⟨N⟩` is the absolute section number. The suffixes `.slf⟨N⟩` and `.slt⟨N⟩` become `.H⟨N⟩` and `.V⟨N⟩`. Of course, this implies a limit of 99 chapters in a document, but do you really need so many chapters (or sections in an article)? The limit of 99 parts does not seem too serious for most documents. See also Chapter 2, item 5).



Table 1.7: Available languages

1. afrikaan (afrikaans)	17. estonian	34. polish
2. arab (arabic) ^a	18. ethiopia (ethiopian)	35. portuges
3. armenian	19. finnish	36. romanian
4. bahasa	20. french (francais)	37. russian ^b
5. basque	21. galician	38. russianb
6. bicig	22. german (austrian)	39. russianc
7. brazil	23. germanb	40. scottish
8. breton	24. greek	41. serbian
9. buryat	25. irish	42. slovak
10. catalan	26. italian	43. slovene
11. croatian	27. lithuanian	44. spanish
12. czech	28. lsorbian	45. swedish
13. danish	29. magyar (hungarian)	46. turkish
14. dutch	30. mongol	47. ukraineb
15. english (american)	31. ngerman	48. usorbian
16. esperant (esperanto)	32. norsk	49. vietnam (vietnamese)
	33. nynorsk	50. welsh

^a The `arab(ic)` language requires the use of `ArabTeX`.

^b The `russian` language is not yet supported, but `russianb` is supported if you use `babel-3.6`; `russianc` is an extra.

1.3 The mtcoff package

When a document has been prepared with the `minitoc` package, it contains many `minitoc` specific commands, most of them being `\dominitoc`, `\faketableofcontents`, and `\minitoc` commands (and their equivalents for lists of figures and tables). If you want to typeset this document without any mini-table, you have just to replace the `minitoc` package by the `mtcoff` package, and all these commands will be ignored. At least two \LaTeX runs will be necessary to get a correct page numbering and correct cross references. It also purges the `.aux`, `.toc`, `.lof`, and `.lot` files from `minitoc` specific spurious commands.

Chapter 2

Frequently Asked Questions

Here is a list of problems and frequently asked questions about `minitoc.sty`. If your version has a number less than 34, please upgrade to version #34.

1. How avoid a page break near the rules before and after the minitoc?
This problem seemed solved since version #8, but version #12 adds better fixes.
2. How about implementing others layouts for the minitoc? Suggestions are welcome.
3. `\` in a contents line makes an error.
Use `\protect\linebreak`.
4. If you reorder chapters, havoc follows. . . minitocs going in wrong chapters.
The best way seems to make one run with the `mtcoff` package replacing the `minitoc` package, then restore the `minitoc` package and re-execute `LaTeX` three times (yes, it is time consuming. . .). Running with the `mtcoff` package ensures that auxiliary files are cleared from “spurious” commands introduced by `minitoc`.
5. This package creates auxiliary files with extensions like `.mtc<N>`. Some operating systems allow only 3 letters extensions. What to do?
No modification is needed: all is automatic since version #28! If you insist to use 3 characters extensions, even on operating systems allowing more, just use the package option `shortext`. Then you will get first

the auto-configuration messages, then a message saying that you will however use short extensions.

6. Do not cheat with the “`chapter`” counter, i.e. do not write horrible things like `\setcounter{chapter}{6}`. The mechanism would break. It is better to add `\chapter` commands, to create empty (but numbered in a legal way) chapters. Since version #10, `minitoc.sty` works with appendices. Version #19 allows to begin with a chapter other than number 1.
7. Some demanding users want to have `minilof`, `minilot` and `minibbl`. First, `minibbl` is an other problem, strongly related to the `BIBTEX`'s dealing with `.aux` files. Look at `chapterbib.sty`, `bibunits.sty`, `multibib.sty`, and `bibtopic`. Version #13 has implemented basic `minilofs` and `minilots`. `Minibbls` are not the aim of this package.
8. This package creates a lot of auxiliary files and some users argue that it is too many. A deep redesign would be necessary to avoid that. Using only one big auxiliary file (or one for all `minitocs`, one for all `minilofs`, ...) would make the reading of such file very slow, and it would be read for each `\miniXXX` macro!
9. How to do `minitocs` (`minilofs` and `minilots`) at levels other than chapter? Here also, some redesign is needed. From version #15, there are `parttocs`, `partlofs` and `partlots` for the part level in book-like and article-like documents, `secttocs`, `sectlofs` and `sectlots` for the section level in article-like documents. Note that you can not have `minitocs` features at chapter and section level in the same document, because doing so would make an unreadable monster. The user must choose the main style of the document accordingly to the size of it (e.g. do not write an article of more than 130 sections: this is a report, or even a book!).

	part	chapter	section
book	*	*	
report	*	*	
article	*		*

10. Since version #23, works with document classes resetting chapter (or section) number at each part.

11. Since version #31, works with the `hyperref` package, thanks to Heiko Oberdiek (`oberdiek@ruf.uni-freiburg.de`). If you add the loading of the `hyperref` package to a document yet using `minitoc`, you will get error message about spurious closing braces. Just let finish the \LaTeX run, then re- \LaTeX the document. There will be no problem if you remove the loading of `hyperref` and add it again: the problem occurs only when you are upgrading from `minitoc #30` to `minitoc #31` (or higher) with a document already processed and adding `hyperref` at the same time! It seems better to process the document with `minitoc #31` (or higher) without `hyperref`, then with `hyperref`, because some internal commands written into the auxiliary files have been modified. If used, the `hyperref` package must be loaded *before* `minitoc`.
12. If you are upgrading from version #30 or lower to version #31 or higher, you should delete the `.aux`, `.toc`, `.lof`, `.lot` of your document, else the first \LaTeX run with version #31 or higher will produce a lot of errors (the next run should be ok).